

Virtual Cement and Concrete Testing Laboratory

Educational Version 2.0 User Guide

Jeffrey W. Bullard*

Materials and Construction Research Division
National Institute of Standards and Technology
Gaithersburg, Maryland USA 20899-8615

This document serves as the user's guide for the educational version of the Virtual Cement and Concrete Testing Laboratory (VCCTL) software, version 2.0. Using the VCCTL software, a user may create 3D microstructures of cement paste made with clinker, calcium sulfate, fly ash, slag, limestone, and other materials. Hydration of these microstructures can be simulated under a variety of curing conditions, and the resulting hardened material can be analyzed for a number of properties including linear elastic moduli, compressive strength, and relative diffusion coefficients. A 3D packing of fine and coarse aggregates in mortar and concrete materials also can be created. The VCCTL software uses a relational database and plotting capabilities to facilitate viewing important characteristics of cement powders, supplementary cementitious materials, fillers, and aggregates. Finally, version 2.0 of the software gives the user control of the execution of his or her simulations.

Keywords: Building technology, cement hydration, computer modeling, concrete testing, microstructure, simulation, virtual laboratory

* Email address: jeffrey.bullard@nist.gov

1	INTRODUCTION	5
1.1	DISCLAIMER.....	5
1.2	INTENT AND USE.....	6
2	INSTALLATION.....	6
2.1	SOFTWARE PREREQUISITES.....	6
2.2	TERMS OF USE AGREEMENT	7
2.3	INSTALLATION FOLDER.....	7
2.4	READY TO INSTALL.....	8
2.5	FINISHING THE INSTALLATION	8
3	LAUNCHING AND CLOSING A SESSION	9
3.1	CLOSING eVCCTL	9
4	REGISTERING AND LOGGING ON.....	10
5	THE MAIN PAGE.....	11
5.1	ANNOUNCEMENTS AND TUTORIALS.....	11
5.2	THE MENU BAR	12
6	LAB MATERIALS.....	13
6.1	CEMENTS	13
	<i>View a cement</i>	<i>13</i>
6.2	SLAGS	18
6.3	FLY ASHES.....	19
6.4	FILLERS.....	20
6.5	AGGREGATES.....	21
7	MIX.....	22
7.1	PREPARE MIX	23
	<i>Specifying the solid cementitious binder.....</i>	<i>23</i>
	<i>Specifying the mix proportions</i>	<i>24</i>
	<i>Specifying simulation parameters.....</i>	<i>26</i>
	<i>Saving the mix</i>	<i>29</i>
7.2	HYDRATE MIX	30

<i>Thermal conditions</i>	30
<i>Aging</i>	31
<i>Saturation conditions</i>	32
<i>Simulation parameters</i>	32
<i>Executing the hydration simulation</i>	33
8 MEASUREMENTS	34
8.1 PLOT HYDRATED PROPERTIES	34
8.2 MEASURE CEMENT/CONCRETE PROPERTIES	36
<i>Elastic Properties Results</i>	38
<i>Transport Properties Results</i>	39
9 MY OPERATIONS	40
<i>Queued operations</i>	40
<i>Running operations</i>	41
<i>Finished operations</i>	41
<i>Canceled operations</i>	42
10 MY FILES	42
10.1 MICROSTRUCTURE OPERATIONS	43
10.2 DISPLAYING MICROSTRUCTURE IMAGES	45
10.3 AGGREGATE OPERATIONS	47
10.4 HYDRATION OPERATIONS	48
10.5 MECHANICAL PROPERTIES OPERATIONS	50
10.6 TRANSPORT PROPERTIES OPERATIONS	51
11 LOGOUT	52
12 APPENDIX I	53
13 APPENDIX II	55
14 BIBLIOGRAPHY	57

1 Introduction

This user's guide provides guidance for using the Virtual Cement and Concrete Testing Laboratory software, Educational Version 2.0 (eVCCTL 2.0). This virtual laboratory software consists of a graphical user interface and the underlying computer models and programs that allow users to create, hydrate, and estimate the performance of 3D cement-based microstructures from a desktop computer. The primary intent of this version is educational, especially to supplement the classroom experience of students studying civil engineering materials technology and materials science.

The main underlying programs for the eVCCTL software have been described previously [Bentz 1997, Bentz 2005, Garboczi 1998], and a large number of applications of these models has been published [Bentz and Haecker 1999, Bentz and Garboczi 1999, Bentz and Jensen 2000, Bentz and Feng, 2000, Bentz and Conway 2001, Bentz and Garboczi 1991, Bullard and Stutzman 2006, Bullard and Garboczi 2006]. This user guide therefore provides a detailed description of the user interface and a few examples of using eVCCTL for educational purposes.

1.1 Disclaimer

This software was developed at the National Institute of Standards and Technology (NIST) by employees of the Federal Government in the course of their official duties. Pursuant to Title 17 Section 105 of the United States Code this software is not subject to copyright protection and is in the public domain. The eVCCTL is an experimental system. NIST assumes no responsibility whatsoever for its use by other parties, and makes no guarantees, expressed or implied, about its quality, reliability, or any other characteristic. We would appreciate acknowledgment, such as an appropriate citation in a publication, if the software is used.

The U.S. Department of Commerce makes no warranty, expressed or implied, to users of eVCCTL and associated computer programs, and accepts no responsibility for its use. Users of eVCCTL assume sole responsibility under Federal law for determining the appropriateness of its use in any particular application; for any conclusions drawn from the results of its use; and for any actions taken or not taken as a result of analyses performed using these tools.

Users are warned that eVCCTL is intended for educational use only and is intended only to supplement the informed judgment of the user. The software package contains computer models which may or may not have predictive value when applied to a specific set of factual circumstances. Lack of accurate predictions by the models could lead to erroneous conclusions with regard to materials selection and design. All results should be evaluated by an informed user.

1.2 Intent and Use

The algorithms, procedures, and computer programs described in this guide constitute a prototype system for a virtual laboratory for the testing of cement and concrete. They have been compiled from the best knowledge and understanding currently available, but have important limitations that must be understood and considered by the user. eVCCTL is intended for use by persons competent in the field of cement-based materials and having some familiarity with computers

2 Installation

2.1 Software Prerequisites

The following requirements must be met for successful installation and running of this distribution of eVCCTL:

Microsoft Windows XP computer¹ (Service Pack 3). Other versions of Windows, such as Windows Vista or Window 7, may or may not be compatible with eVCCTL. Distributions are available for Linux operating systems; please contact the author for details.

A minimum of 2 GB RAM and minimum hard disk space of 20 GB for long-term use of the software. Multiprocessor architectures with expanded shared memory, such as 16 GB, are commonly available and are recommended for the simultaneous execution of multiple simulations without loss of performance.

Java Development Kit (JDK) 1.6, Update 20, or a more recent update. Go to <http://www.oracle.com/technetwork/java/javase/downloads/jdk6-jsp-136632.html> to download the latest release of the JDK and follow the installation instructions given there.

Mozilla Firefox web browser, Version 3.0. Not required for installation, but other non-standard web browsers, such as Microsoft's Internet Explorer, give erratic results when running the software.

To install eVCCTL, drag the `evcctl-2.0-installer-windows.exe` icon to the Desktop. Once it has been copied to the Desktop, double-click on the installation icon. A series of windows will guide you through the installation process as follows.

¹ Certain commercial equipment and/or materials are identified in this report in order to adequately specify the experimental procedure. In no case does such identification imply recommendation or endorsement by the National Institute of Standards and Technology, nor does it imply that the equipment and/or materials used are necessarily the best available for the purpose.

Installation


2.2 Terms of Use Agreement

This dialog requires you to acknowledge the software disclaimer. If you accept the disclaimer agreement, you proceed with the installation by pressing the “Next” button. Otherwise, you will not be able to install and use the eVCCTL software.



2.3 Installation Folder


You may install eVCCTL in any location on your computer, provided that you have the adequate read/write permissions. The default path and folder is C:\Program Files\vcctl. You may accept that default or change it to another location. However, **THE FINAL FOLDER ON THE PATH MUST BE NAMED vcctl IN ALL LOWERCASE LETTERS.** The software will not work properly if it is not installed in a folder named vcctl.




Installation

2.4 Ready to Install

The next dialog indicates that the software is ready to install. Clicking the “Next” button will begin the installation.



The last step of the installation is to unpack a rather large data folder. This step can consume several minutes, during which time it will appear that nothing is happening. Please be patient while the data folder unpacks.



2.5 Finishing the Installation

When the final step is completed, a final dialog box will appear. Just click on the “Finish” button to close this dialog box.

3 Launching and Closing a Session

Before running eVCCTL for the first time, it is helpful to make Mozilla Firefox your default web browser. To do this, open Mozilla Firefox. If it is not already your default browser, a dialog box should appear asking you if you want to make it your default browser. Click “Yes” and then close the browser after it opens.

If the installation was successful, then eVCCTL can be launched from the Desktop by double-clicking on the Desktop icon labeled eVCCTL 2.0:



A Java console window will appear on the desktop, with a lot of information scrolling through it:

```
eVCCTL 2.0
at org.apache.derby.jdbc.Driver40.getNewEmbedConnection(Unknown Source)
at org.apache.derby.jdbc.InternalDriver.connect(Unknown Source)
at org.apache.derby.jdbc.AutoloadedDriver.connect(Unknown Source)
at java.sql.DriverManager.getConnection(Unknown Source)
at java.sql.DriverManager.getConnection(Unknown Source)
at nist.bfrl.vcctl.database.UserDatabase.getConnection(UserDatabase.java:
:35)
at nist.bfrl.vcctl.database.UserDatabase.getUserNames(UserDatabase.java:
78)
at nist.bfrl.vcctl.execute.RunningOperations.run(RunningOperations.java:
90)
at java.lang.Thread.run(Unknown Source)
Caused by: java.sql.SQLException: Database 'C:\Program Files\vcctl\usr\hazel\dat
abase\vcctl_user' not found.
at org.apache.derby.impl.jdbc.SQLExceptionFactory.getSQLException(Unknown
Source)
at org.apache.derby.impl.jdbc.SQLExceptionFactory40.wrapArgsForTransport
AcrossDBMS(Unknown Source)
... 18 more
java.sql.SQLException: Database 'C:\Program Files\vcctl\usr\hazel\database\vcctl
_user' not found.
at org.apache.derby.impl.jdbc.SQLExceptionFactory40.getSQLException(Unkn
own Source)
at org.apache.derby.impl.jdbc.Util.newEmbedSQLException(Unknown Source)
at org.apache.derby.impl.jdbc.Util.newEmbedSQLException(Unknown Source)
```

You must never close this console window while eVCCTL is running. Under ordinary circumstances, you may ignore this console window entirely. You may even minimize the window to your desktop tray if desired, but do not close it.

WARNING: You must **never** close the Java console window during an active session of eVCCTL. Doing so will cause eVCCTL to terminate immediately and, in some cases, a portion of the database that keeps track of your running operations may also become corrupted. It is safest to simply minimize the console window to your desktop tray and leave it there while you are using eVCCTL.


A few moments after the Java console window appears, your default web browser should open to the main login page of eVCCTL. Again, if this is not Mozilla Firefox, then you could observe unexpected or erratic behavior.

3.1 Closing eVCCTL

To properly shut down eVCCTL, follow these steps:

Launching and Closing


1. Wait for all running operations to finish. Alternatively, you could cancel all the running operations if needed (this will be described in detail below).
2. Close the web browser
3. Open the Java console window and press `Ctrl-C`. After a brief pause, you will be asked, "Terminate batch job (Y/N)?". Type "y" and press the Enter button. The Java console window will close.



```
C:\Program Files\vcctl\scripts>cd ..\src
C:\Program Files\vcctl\src>java -jar "UcctlWrapper.jar"
2010-05-12 16:40:14.100:INFO:Logging to StdErrLog::DEBUG=false via org.eclipse.
jetty.util.log.StdErrLog
2010-05-12 16:40:14.131:INFO::jetty-7.0.1.v20091125
2010-05-12 16:40:14.359:INFO:Extract jar:file:/C:/Program%20Files/vcctl/src/vc
ctl.war!/ to C:\Documents and Settings\bullard\Local Settings\Temp\Jetty_0_0_0_0
8080_vcctl.war_vcctl_pjnfun\webapp
May 12, 2010 4:40:17 PM org.apache.struts.action.ActionServlet initChain
INFO: Loading chain catalog from jar:file:/C:/Program%20Files/vcctl/src/lib/stru
ts-tiles-1.3.8.jar!/org/apache/struts/tiles/chain-config.xml
May 12, 2010 4:40:17 PM org.apache.struts.action.ActionServlet initChain
INFO: Loading chain catalog from jar:file:/C:/Documents%20and%20Settings/bullard
/Local%20Settings/Temp/Jetty_0_0_0_8080_vcctl.war_vcctl_pjnfun/webapp/WEB-IN
F/lib/struts-tiles-1.3.8.jar!/org/apache/struts/tiles/chain-config.xml
May 12, 2010 4:40:17 PM org.apache.struts.tiles.TilesPlugin initDefinitionsFacto
ry
INFO: Tiles definition factory loaded for module ''
2010-05-12 16:40:17.631:INFO:Started SelectChannelConnector@0.0.0:8080
Terminate batch job (Y/N)? y
```

4 Registering and Logging On

eVCCTL is a standalone desktop application, but it allows for some form of data privacy among multiple users on the same computer. For this reason, a session begins with logging on with a user name and password.



Connection

Login: Password:

Don't have an account? [Register!](#)

The first time you launch a session, you will not have a user name or password, so you must register with the database by clicking on the "Register!" link. This link will take you to a registration form shown below:

Enter your desired user name in the first box. If the user name is valid and has not been taken by someone else, you will see a green checkmark as shown. Otherwise, a red X will appear and you will be prompted to choose another name.

Next, enter your desired password. You must confirm the password in the adjacent text field, and if the two text fields agree, you will again see a green checkmark as shown.

Finally, enter your e-mail address in the bottom text box and confirm the address in the adjacent text box. E-mail addresses are not currently used by the

Logging On

application, but may be used in a future release to remotely notify users of completed operations, errors, or other important events.

When all the information has been entered properly (i.e., green checkmarks everywhere) then click the “Submit my registration” button. You will then be taken back to the login page, where you can enter your new user name and password.

Username:	
Enter your desired username:	<input type="text" value="hazel"/> ✓
Password:	
Enter your password:	<input type="password" value="*****"/> Confirm your password: <input type="password" value="*****"/> ✓
Email address:	
Enter your email address:	<input type="text" value="hazel@someaddress.net"/> Confirm your email address: <input type="text" value="hazel@someaddress.net"/> ✓
<input type="button" value="Submit my registration"/>	

5 The Main Page

A successful login will open the main page of the application. There are two parts to this page: (1) a section for announcements and streaming video tutorials, (2) a running Menu Bar in gray near the top.

5.1 Announcements and Tutorials

This section briefly introduces you to the major features of the eVCCTL application and also features a “Lab Tour”. The lab tour consists of a series of streaming video tutorials designed to step you through each of the major features and acquaint you with the procedures for running and monitoring different operations. Note that the lab tour requires (1) an internet connection and (2) a QuickTime plugin or other compatible streaming video plugin for your browser. Downloading and installing Apple’s free QuickTime player should automatically update your browser with the plugin.

The tutorials and this user guide are designed to be used together. One should view the tutorials first, then consult this guide for further details.

Menu Bar

Home | Lab Materials | Mix | Measurements | My Operations | My Files | Logout

Welcome to VCCTL Educational Version

The Virtual Cement and Concrete Testing Laboratory (VCCTL) provides a virtual laboratory environment for testing cement and concrete. With VCCTL, you can create virtual specimens of cement paste, mortar or concrete. You can simulate the hydration of these specimens and measure a diverse set of physical properties.

Features

- Viewable materials database for cements, aggregates, fly ash, slag, and inert fillers
- User interface remembers what operations you have performed and where your files are
- Create a 3D cement paste, mortar, or concrete microstructures with real-shape particles or spheres
- Simulate hydration of your microstructure for a prescribed time
- Flexible plotting capability for viewing cement hydration results
- Calculate linear elastic properties of hydrated cement, mortar, or concrete
- Calculate effective diffusion coefficient of hydrated cement
- Full control of your operations, including ability to cancel or delete
- Export your operation data to use in other applications

Take a Lab Tour
Requires Internet Connection and QuickTime Player
► Exploring Cement Materials

5.2 The Menu Bar

The menu bar is a persistent feature on all pages of the eVCCTL application, and enables you to quickly navigate from one part of the lab to another. The menu items are:

Home: The main page

Lab Materials: A multi-part page enabling you to examine the different materials stored in the eVCCTL database

Mix: A two-part page where you can make and hydrate virtual mixes of cement paste, mortar, or concrete

Measurements: A two-part page enabling you to plot the changes in properties of a material as it hydrates, or to calculate the linear elastic properties, compressive strength, and transport properties of your mix.

My Operations: Enables you to view the state of your requested operations (queued, running, finished, or canceled)

My Files: A listing of all your operations, complete with the ability to view any file in any operation or to export any file for further analysis by another application.

Logout: Provides a way to logout of the system or switch users.

Each of these menu items will be described in detail in the following sections.

6 Lab Materials

Click on the “Lab Materials” tab on the main menu, and you will be taken to a page that has a submenu with five tabs:



Each tab takes you to a page that enables you to view the properties of the relevant material component in the eVCCTL database.

6.1 Cements

This page enables you to view the inventory of cements stored in the eVCCTL database, along with a number of their physical and chemical properties. There are two sections to this page: (1) View a cement, and (2) View a cement data file.

NOTE: Frequently you will see a small question mark icon, , near a feature on page. This is a tool-tip icon; clicking on it will open a blue textbox that gives brief information about the feature in question.

View a cement

The top section of the page has (1) a pull-down menu to select the cement that you want to view, (2) a view of a false-color scanning electron microscope (SEM) image of the cement which has been color-coded to reveal the spatial distribution of the mineral phases, (3) an text box with additional information about the cement, and (4) a collection of quantitative data on the cement, under the heading “Cement data” that is initially collapsed and hidden when the page opens.

Selecting a different cement in the pull-down menu will update each of these fields to display the relevant data for that cement. The characterization techniques used to generate these data have been described in detail in previous publications [[Bentz and Stutzman 1994](#), [Bentz and Stutzman 1999](#)].

Segmented SEM image

This section shows a single image field from a scanning electron micrograph that has been colored to indicate the locations of the various cementitious mineral phases in the cement powder. A key to the color mappings is provided with each image.

Information text box

The text box immediately below the image displays information about the cement, including a brief description, the original source of the cementitious sample, the date when the cement was either received or analyzed, and the fineness measured either by the air permeability test (Blaine, ASTM C204 [ASTM 2008]) or by laser diffraction from a dilute suspension of cement powder particles in isopropyl alcohol.


Cements
Slags
Fly Ashes
Fillers
Aggregates

Cement Materials Inventory

▼ View a cement

Name: ?

Segmented SEM image



C_3S	C_2S	C_3A	C_4AF
			
K_2SO_4	Na_2SO_4	Gypsum	$CaCO_3$
			
SiO_2	Slag	Pore	
			

Desc	CCRL Cement 140
Source	Cement and Concrete Reference Laboratory (CCRL) Proficiency Sample
Date	Released in January 2001
Fineness	403.2 m ² /kg (based on air permeability test)

▶ Cement data ?

Cement data

This section is initially “collapsed” when the page opens. It can be displayed by clicking on the small grey triangle next to the “Cement data” subheading.

The fully displayed section contains a number of read-only text boxes and a couple of pull down menus that are described in the following list.

Lab Materials

PSD: This is a pull-down menu pointing to the file that contains the information on the particle size distribution (PSD) of the cement. In this educational version of VCCTL, selecting a different item on this menu has **no effect** on the cement. The only way to modify the PSD of a cement is to modify the file associated with the

- ▼ Cement data ?
 PSD: cement140 psd ?
 Alkali: alkalicem140 ?

PFC ?		X-ray Diffraction Data ?		
		PHASE	MASS %	VOLUME %
0.6865	0.6878	-----		-----
0.1611	0.1195			
0.0813	0.1107	C3S	64.660004	65.468468
0.0711	0.0820	C2S	16.500000	16.044165
		C2S-alpha	0.390000	0.379226
		C4AF	7.670000	6.558333
		C3A-cubic	4.730000	4.978809
		C3A-orth.	0.710000	0.742447
		Mg/Ca	0.480000	0.405001
		K2SO4	0.310000	0.371416
		Langbeinite	0.000000	0.000000

Sil ?	C ₃ S ?	C ₄ AF ?	C ₃ A ?
60	60		60
0 0.356035	0 0.257695		0 0.051562
1 0.290914	1 0.198794		1 0.029239
2 0.251960	2 0.165669		2 0.020538
3 0.223482	3 0.142123		3 0.015071
4 0.203433	4 0.125853		4 0.011600
5 0.188647	5 0.114120		5 0.009147
6 0.177226	6 0.105059		6 0.007358
7 0.168146	7 0.097786		7 0.006049
8 0.161025	8 0.092049		8 0.005030
9 0.155393	9 0.087358		9 0.004308

Na ₂ SO ₄ ?	K ₂ SO ₄ ?	Alu ?

cement (e.g., cement140 psd as shown in the figure). Please refer to the next section, **View a cement data file**, for more information on how to modify the PSD of a cement.

Alkali: This is a pull-down menu pointing to the file that contains the information on the alkali content of the cement, including the total equivalent K₂O and Na₂O content as well as the readily-soluble fraction of each. In this educational version of VCCTL, selecting a different item on this menu has **no effect** on the cement. The only way to modify the alkali content of a cement is to modify the file associated with the cement (e.g., alkalicem140 as shown in the figure). Please refer to the next section, **View a cement data file**, for more information on how to modify the alkali content of a cement.

PFC: PFC is an acronym for Phase Fractions in Clinker. The data are displayed as either four or six rows of two columns each. The first row is for alite (C₃S²), the

² Where it is convenient and unlikely to cause confusion, conventional cement chemistry notation is used in this guide. C = CaO, S = SiO₂, A = Al₂O₃, F = Fe₂O₃, H = H₂O

Lab Materials

second row for belite (C_2S), the third row for tricalcium aluminate (C_3A), and the fourth row for tetracalcium aluminoferrite (C_4AF). If a fifth and sixth row are present, they represent arcanite (K_2SO_4) and thenardite (Na_2SO_4), respectively. The left column indicates the volume fraction of the associated phase, on a total clinker volume basis, and the right column indicates the surface area fraction of the associated phase, on a total clinker surface area basis. The sum of each column should be 1.0.

X-ray Diffraction Data: This field displays the results of a quantitative X-ray powder diffraction analysis of the cement using Rietveld refinement. The data are not used by the eVCCTL software, but are merely present to provide additional information to the user.

Sil, C_3S , C_4AF , C_3A , Na_2SO_4 , K_2SO_4 , Alu: These fields display the kernels for the two-point correlation function calculated for the combined silicates, C_3S , C_4AF , C_3A , Na_2SO_4 , K_2SO_4 , and combined aluminates, respectively. These data are used to distribute the clinker phases among the cement particles that are created when a mix is requested. One or more of these fields may be blank.


In the educational version of VCCTL, none of these cement data may be permanently changed in the database. The text boxes are read-only and may not be modified. However, certain properties of a cement may be temporarily modified at the time when a mix is made (see [Section 7.1](#) for more information).

Mass fractions of sulfates

Three calcium sulfate carriers are recognized in eVCCTL: gypsum (calcium sulfate dihydrate), bassanite (hemihydrate), and calcium sulfate anhydrite. This section shows the mass fractions of each of these carriers found in the cement, on a total solids basis. In eVCCTL, these values may not be permanently modified in the database. However, they may be temporarily changed at the time when a mix is made (see [Section 7.1](#) for more information).

View a cement data file

This section is also collapsed when the page first opens. It can be displayed by clicking on the small grey triangle next to the heading “View a cement data file”.



There are a number of different auxiliary data files that are used by eVCCTL to make mixes or simulate the hydration of materials, and this section enables the user to view and modify some of those data files. The left text box contains the actual data, and the right text box contains information on the formatting of the data file. Each type of data file is described in the following list:

psd: These files contain information on the particle size distribution of the cement powder. The left column is the equivalent spherical diameter in micrometers (i.e., the diameter of a sphere having the same volume as the irregularly shaped particle), and the right column is the volume fraction of particles having an equivalent spherical diameter between that row and the following row. Therefore, these data describe a discrete probability density function (PDF) for the particle sizes.

alkali_characteristics: These files contain information on the potassium and sodium content of the cement on a total solids basis. This data file has four or six rows. The first and second rows are the mass per cent equivalent total Na_2O and K_2O , respectively. The third and fourth rows are the mass per cent readily soluble Na_2O and K_2O , respectively. The fifth and sixth rows, if they are present, are the mass per cent Na_2O and K_2O added as NaOH and KOH to the mix water, respectively.

slag_characteristics: There is only one of this kind of data file in eVCCTL. It describes the physical and chemical properties of both the slag and the slag gel hydration product. This file can be modified but will have no effect on the calculations made by eVCCTL. More information on the meaning of each parameter is provided in [Section 6.2](#) on Slags below.

parameter_file: There is only one of this kind of file in eVCCTL. It catalogs the values of several dozen empirical parameters that are used by the program that simulates hydration of cement pastes. The meaning of each parameter is beyond the scope of this guide.

chemical_shrinkage_file: In the full version of VCCTL, users can calibrate the time scale for hydration simulations using experimentally determined chemical shrinkage data. This file contains the measured data as an example, but this calibration feature is disabled in eVCCTL, so changing the file will have no effect on the calculations.

calorimetry_file: In the full version of VCCTL, users can calibrate the time scale for hydration simulations using experimentally determined isothermal calorimetry data. This file contains the measured data as an example, but this calibration feature is disabled in eVCCTL, so changing the file will have no effect on the calculations.

Users may alter any of the data files and save them by pressing the “Save” button below the text boxes. For example, if a user manually modifies the `cement140_psd` data file and saves the changes, the modified PSD data will be used any time that `cement140_cement` is used to create a mix.

A copy of each original data file is stored in the database, so if a user wishes to return to the original data, the “Restore” button can be pressed, followed by the “Save” button. **NOTE:** The user **must** press the “Save” button after restoring original data or the previously modified data will remain.

6.2 Slags

The slag material inventory page consists of a pull-down menu to select the slag to view (there is only one slag in the eVCCTL database), along with a textbox displaying the specific gravity of the slag and a second pull-down menu pointing to the file for particle size distribution. Again, in eVCCTL these fields cannot be modified or, in the case of the PSD file, can only be modified indirectly by changing the contents of the associated PSD file (e.g. cement141 psd) on the Cements page.

A second section, “Slag properties and description” is initially collapsed when the page opens, but can be expanded by clicking on the small grey triangle next to the heading. This section displays the chemical and physical properties that the eVCCTL hydration model needs to be able to simulate the hydration of the slag in a blended cement. The properties are self-explanatory, and the tool-tip can be used to gain further information on some of them. Notice that some of the properties relate to the slag itself, some relate to the slag “hydration product”, and some must be specified for both the slag and the hydration product. In eVCCTL, these properties cannot be edited, but are displayed primarily for informational purposes.

▼ Slag properties and description ?

Property	Slag	Slag gel hydration product
Molecular mass (g/mol)	2492.4	4307.085
Density (g/cm ³)	2.991	2.35
Molar volume (cm ³ /mol)	833.2998996990973	1832.8021276595744
Ca/Si molar ratio	0.97	1.25
Si per mole of slag ?	17.0	
H ₂ O/Si molar ratio		5.059
C ₃ A per mole of slag ?		0.0
Base slag reactivity ?	1.0	

Description: ?

6.3 Fly Ashes

The fly ash material inventory page consists of a pull-down menu to select the fly ash to view (there is only one fly ash in the eVCCTL database), along with a textbox displaying the specific gravity of the fly ash and a second pull-down menu pointing to the file for particle size distribution. Again, in eVCCTL these fields cannot be modified or, in the case of the PSD file, can only be modified indirectly by changing the contents of the associated PSD file (e.g. `cement141_psd`) on the Cements page. Unlike slags, however, fly ash materials consist of multiple phases. Therefore, another field is displayed to indicate whether the phases are to be distributed on a particle basis (i.e. each fly ash particle is a single phase) or on a pixel basis (i.e. each particle contains multiple phases distributed randomly pixel by pixel). In eVCCTL, the fly ash in the database is set to distribute its phases on a particle basis. Although the user can click on the other radio button to choose the pixel-based distribution, this has no real effect because the ability to save the modified fly ash is disabled in this educational version.

The screenshot shows the 'Fly Ash Material Inventory' interface. At the top, there are navigation tabs: 'Cements', 'Slags', 'Fly Ashes', 'Fillers', and 'Aggregates'. The 'Fly Ashes' tab is selected. Below the tabs is the title 'Fly Ash Material Inventory'. Underneath is a section titled 'View a fly ash' with a dropdown arrow. The dropdown menu is open, showing the following fields:

- Name: flyash01.fly
- Specific gravity (SG): 2.77
- Particle Size Distribution (PSD): cement141_psd
- Distribute flyash phases randomly:
 - on particle basis, OR
 - on pixel basis

 Below these fields is a collapsed section titled 'Fly ash properties and description'. At the bottom of the form are four buttons: 'Cancel', 'Save', 'Save as...', and 'Delete'.

Like the slag inventory page, the fly ash page has a second section, initially collapsed when the page opens, for other fly ash properties. In this case, the fly ash properties are simply the volume fraction of the various phases comprising the fly ash. The seven eligible phases are shown in the accompanying figure. Again, the values in the table cannot be edited in eVCCTL but are displayed only for informational purposes. The phase distribution shown is similar to a fly ash that was characterized in 2004 at NIST [[Feng and Garboczi 2004](#)].

▼ Fly ash properties and description

The fraction of either particles or pixels in the flyash that belong to each phase is given in the table below. The sum of the phases in the table below will be filled with inert material.

Phase	Fraction
Aluminosilicate glass	0.5
Calcium Aluminum Disilicate	0.45
Tricalcium Aluminate	0.0
Calcium Chloride	0.0
Silica	0.03
Anhydrite (CaSO4)	0.02
Sum	1.0

Description:
 Generic fly ash material. Chemical composition and phase distribution reported in X. Feng, E.J. Garbocz, D.P. Bentz, P.E. Stutzman, "Effect of the degree of hydration of blended cement pastes by a scanning electron microscope point-counting procedure," *Cem. Concr. Res.* 34 [10] (2004) 171-178.

6.4 Fillers

Inert fillers have only two properties of interest: specific gravity and particle size distribution. The inventory of fillers in eVCCTL consists of three materials, (1) α -quartz (SiO_2) with a specific gravity of 2.62, (2) corundum (Al_2O_3) with a specific gravity of 4.05, and (3) periclase (MgO) with a specific gravity of 3.78. All three inert fillers have cement141 psd to describe their particle size distribution. In eVCCTL, these properties cannot be changed.

Cements Slags Fly Ashes **Fillers** Aggregates

Filler Material Inventory

▼ View inert fillers

Name: periclase

Specific gravity: 3.78

Particle Size Distribution (PSD): cement141 psd

Description:
 Inert filler with density consistent with periclase
 Cement 141 from the CCRL proficiency sample program

Cancel Save Save as... Delete

6.5 Aggregates

Coarse and fine aggregates are included in the eVCCTL database for the purposes of creating mortar and concrete mixes. Three coarse aggregate sources and four fine aggregate sources have been characterized for particle shape, specific gravity, and linear elastic moduli. The shape characterization procedure involves capturing a 3D image of a packing of the aggregate particles, using X-ray computed tomography, and then analyzing the shape of individual particles by spherical harmonics. The procedure is described in [[Garboczi 2002](#)].

▼ **Fine aggregate**

Fine aggregate source: ⓘ

— **Image and shape data**

Image



Shape Data

Number of particles analyzed: 533	
Mean L/T = 2.564 +- 0.777	
Range of L/T = [1.165, 5.906]	
Mean W/T = 1.688 +- 0.467	
Range of W/T = [1.009, 3.564]	
Distribution (%):	
W/T	

The aggregate materials inventory consists of one section for coarse aggregates and one for fine aggregates. Both sections are collapsed when the page first appears and can be opened by clicking on the small grey triangle next to the respective headings. Each section is identical except for the materials it displays, so the accompanying figures will illustrate the features for the fine aggregates only.

When the coarse or fine aggregate section is expanded, there is a pull-down menu to choose which aggregate source to examine. Below that is a section showing a color photograph of a small sample of the aggregate and an accompanying table that summarizes the gross shape data for the aggregate such as the distribution of ratios of length to width (L/W) and width to thickness (W/T)³. In the table, the mean and range of L/T and W/T are provided, and below that a table showing the distribution of particles with given L/T and W/T. These data come from the spherical harmonic analysis, but it is useful to remember that the spherical

³ In aggregate terminology, the length is the greatest linear dimension of an aggregate particle, the width is the greatest linear dimension in any direction perpendicular to the length axis, and the thickness is the greatest linear dimension the direction that is simultaneously perpendicular to both the length and the width.

Lab Materials

harmonic data in the database contain much more information about particle shape, enough to reproduce the 3D shape of a given particle of any size and rotational orientation in space.

Below the image and shape data, some physical properties of the aggregate are displayed, including the specific gravity, bulk modulus (in GPa) and shear modulus (in GPa). These fields cannot be edited by the user, but are displayed for informational purposes and so the user can see the values used for input in the calculations involving these materials. Finally, a text box displays other information about the aggregate, including a descriptive name, the source and intended use of the aggregate and, in some cases, the basic mineralogical content.

Specific gravity:

Bulk modulus: GPa

Shear modulus: GPa

Description:

Desc	AASHTO Proficiency Sand #39
Name	MA114F-3-fine
Info	AASHTO Materials Reference Laboratory
Info	Proficiency sample #39
Info	For hot-mix asphalt



7 Mix

With some knowledge of the types of materials and their properties that are stored in the eVCCTL database, we turn now to the part of the software that enables one to create mixes and cure them. This part of the software is accessed through the “Mix” tab on the main menu bar, and has a submenu for accessing two pages, one for creating a mix and one for simulating its hydration.

A Note on the Operating Principles of VCCTL Programs: Before describing these parts of the software, it is useful to understand the underlying operating principles of the programs that create the mixes and simulate hydration. VCCTL software (both eVCCTL and the full VCCTL version) are based on a “digital image” approach to representing microstructure. In this approach, microstructures are mapped onto a regular 3D grid of cubic volume elements, often called pixels or voxels. For cement pastes, each voxel is 1 μm on a side, but for larger scale packings of fine or coarse aggregates the voxel size depends on the smallest particle that will be placed. When a cement paste microstructure is created on this voxel grid, each voxel is occupied by exactly one “phase” (e.g., C_3S , slag, saturated porosity, etc.). In this way, the programs that lie behind the VCCTL user interface are able to accurately reproduce microstructures that capture the desired phase assemblage, water/cement ratio, particle size and shape distribution, and surface areas.

Prepare Mix

Simulating hydration of these initial microstructures involves rule-based interactions among the voxels in the microstructure. The rules are designed to mimic the various chemical reactions and mass transport that occur during hydration. As a result, the 3D digital image microstructure is incrementally changed to simulate microstructure development. This process introduces new hydration product phases such as C-S-H gel, CH, ettringite, and several others.

The full details of the operating principles for the digital image approach can be found in other publications [[Bentz 1997](#), [Bentz 2005](#)]. A discussion of computational tools that have been developed to analyze the properties of digital image microstructures can be found in [[Garboczi and Bentz 1999](#)]. Some of the artifacts and limitations of digital image approaches are described in [[Garboczi and Bentz 2001](#)].

7.1 Prepare Mix

This page is used to create an initial 3D cement microstructure consisting of particles of cement clinker, calcium sulfate carriers, and other selected compounds in water, as well as simulated packings of fine and coarse aggregates when the paste is acting as the binder in a mortar or concrete. There are three main steps involved in creating the mix: (1) specifying the solid cementitious binder properties, (2) specifying the mix proportions of the solid portion of the binder with water and aggregate, and (3) specifying the system size and other miscellaneous simulation parameters. Each of these steps is now described.

Specifying the solid cementitious binder

The principal component of the binder is one of the portland cements, which may be selected from among those in the database using the pull-down menu selector. Once the cement is selected, the volume fractions and surface area fractions of the clinker minerals may be modified for the mix if desired by expanding the section “Modify phase distribution of the *clinker*”. The default values displayed in the tables are those stored in the database for the corresponding cement when it was characterized as already described. The table keeps a running sum of the two columns, which should both add to 1.0. If the user modifies the values in the columns in such a way that one or both columns do not sum to 1.0, the columns will be re-normalized to 1.0 when the mix is created.

The chosen cement also has default values for the mass fractions of the calcium sulfate carriers (dihydrate, hemihydrate, and anhydrite) which can be reviewed and modified by expanding the section headed “Modify calcium sulfate amounts in the *cement*”. Remember that the displayed values are given on a total solid cement basis, and that all values are displayed as fractions, not percentages.

Prepare Mix

Step 1: Prepare mix ?

Binder ?

Choose a cement: cement140

▼ Modify phase distribution in the *clinker*

Phase	Volume fraction	Surface area fraction
C ₃ S	0.6865	0.6878
C ₂ S	0.1611	0.1195
C ₃ A	0.0813	0.1107
C ₄ AF	0.0711	0.0820
K ₂ SO ₄	0.0000	0.0000
Na ₂ SO ₄	0.0000	0.0000
Sum:	1.000	1.000

The last part of specifying the solid binder is to select the type and quantity of any supplementary cementitious materials (SCMs) or fillers. The categories for these materials are (1) fly ash, (2) slag, (3) inert filler, (4) silica fume, (4) limestone (CaCO₃), and (5) free lime (CaO). For fly ash, slag, and inert filler, the materials may be selected from the accompanying pull-down menu selector from those available in the database, as already described in [Section 6](#). For silica fume, limestone, and free lime, the composition and specific gravity are assumed fixed, and the user is asked only to specify the particle size distribution by selecting the file for the PSD from one of those in the database. Recall that the PSDs associated with each file can be viewed on the Lab Materials page as described in [Section 6.1](#). Once the material and characteristics are selected, the user may specify either the mass fraction or volume fraction that the material will occupy on a total solid binder basis. This is equivalent to specifying a *replacement* level for each component. **Note** that the total fraction of cement in the binder is reduced as the fractions of these other materials is increased. Note, if the mass fraction is specified, then the volume fraction will be automatically calculated and displayed based on the specific gravities of all the components. Similarly, specifying the volume fraction will cause the mass fraction to be automatically calculated and displayed.

Specifying the mix proportions

When the solid portion of the binder is specified, the next section can be used to specify the water/binder mass ratio (w/b) using the pull-down menu selector. The options for the w/b value cover the range normally used for concrete and also include the value 0.485, the latter which is used for ASTM C109 mortar cube compressive strength specimens [[ASTM 2008](#)]. Read-only text fields for viewing the

Prepare Mix

mass fractions and volume fractions of solid binder and water corresponding to the selected w/b ratio.

▼ Modify calcium sulfate amounts in the *cement*

Sulfate form	Mass fraction	Volume fraction
Dihydrate	0.0039	0.0054
Hemihydrate	0.022	0.0258
Anhydrite	0.016	0.0197

▼ Add SCM or filler to the *binder* ?

	PSD/characteristics file	Mass Fraction	Volume Fraction
<input type="checkbox"/> Add Fly Ash	flyash01.fly	0.0	0.0
<input type="checkbox"/> Add Slag	slag01.slg	0.0	0.0
<input type="checkbox"/> Add Inert Filler	corundum	0.0	0.0
<input type="checkbox"/> Add Silica Fume	cement140 psd	0.0	0.0
<input type="checkbox"/> Add CaCO ₃	cement140 psd	0.0	0.0
<input type="checkbox"/> Add Free Lime	cement140 psd	0.0	0.0
Cement		1.0	1.0

This section also includes the option to add coarse or fine aggregate to the mix to create a mortar or concrete. To add aggregate, click on the checkbox next to the coarse or fine aggregate. When this is done, the text boxes for the mass fraction and volume fraction, initially disabled, become enabled and the user can type in the desired mass fraction or volume fraction, on a *total mortar or concrete basis*.

Mix ?

	Mass fraction	Volume fraction
Binder	0.6897	0.4129
Water	0.3103	0.5871
Water/Binder ratio	0.45	
<input type="checkbox"/> Add Coarse Aggregate	0.0	0
<input type="checkbox"/> Add Fine Aggregate	0.0	0

In addition, when one of the aggregate checkboxes is selected, a new section appears below it, initially collapsed, called "Change properties". Expanding this section enables the user to specify the aggregate source, specific gravity, and grading (or size distribution).

Prepare Mix

Add Fine Aggregate 0.65 0.5694

▼ Change properties

Aggregate source: AASHTO Proficiency Sand 39

Specific gravity: 2.65

Grading: ASTM-C109.gdg

Sieve	Diameter (mm)	Fraction Retained
No. 5	4.000 - 4.5	0.0
No. 6	3.350 - 4.000	0.0
No. 7	2.800 - 3.350	0.0
No. 8	2.360 - 2.800	0.0
No. 10	2.000 - 2.360	0.0
No. 12	1.700 - 2.000	0.0
No. 14	1.400 - 1.700	0.0
No. 16	1.180 - 1.400	0.0
No. 18	1.000 - 1.180	0.0
No. 20	0.850 - 1.000	0.0
No. 25	0.710 - 0.850	0.02
No. 30	0.600 - 0.710	0.0
No. 35	0.500 - 0.600	0.28
No. 40	0.425 - 0.500	0.0
No. 45	0.355 - 0.425	0.45
No. 50	0.300 - 0.355	0.0

Notice that changing the specific gravity of the aggregate causes the volume fractions of the aggregate, binder, and water all to change in response. Finally, aggregate grading is displayed in tabular form using the customary sieve designations to indicate the size bins that are used. The user may specify the grading by typing in the mass fraction of aggregate retained in each sieve. The sum of the mass fractions in the table should be 1.0, but it will be normalized to 1.0 if not. eVCCTL comes with one pre-selected fine aggregate grading that corresponds to the grading specified in the ASTM C 109 mortar cube compressive strength test [[ASTM 2008](#)]. The coarse aggregate section also comes with a default aggregate grading, but the default grading does not correspond to any particular test.

Note: In the full version of VCCTL, the aggregate grading specified manually by the user can be saved in the database for easy retrieval in subsequent mixes, but in eVCCTL this feature has been disabled.

Specifying simulation parameters

After the mix proportions are specified, the user may optionally select or modify any of several simulation parameters, each of which is now described.

Random number generator seed: When the virtual microstructures are created, random numbers are used to randomly select the positions of particles as they are added, to stochastically distribute the clinker phases within the constraints

Prepare Mix

of the two-point correlation functions, and a variety of other tasks. The random number generator used in the VCCTL programs require an initial “seed” value, which must be a negative integer. Under ordinary circumstances, the seed value will be chosen automatically, but the user may also specify a particular seed value, if desired, by checking the box and typing a negative integer in the text box. If a non-negative integer number is typed in the box, it will be ignored.

Simulation parameters ?

Use my own random number generator seed: 0

Use real particle shapes with shape set: None

System size for the binder:

x dimension	100	microns
y dimension	100	microns
z dimension	100	microns

System size for the concrete:

x dimension	4.00	millimeters
y dimension	4.00	millimeters
z dimension	4.00	millimeters
Resolution	0.10	millimeters/pixel

Create the 3D aggregate packing

Real particle shapes: Check this box if you want the *cement particles* in the microstructure to have realistic shapes. As already described, the 3D shapes of aggregate particles have been characterized by spherical harmonic analysis and stored in the VCCTL database to recreate realistic aggregate packings. A nearly identical procedure has been used to characterize the particle shapes of several different portland cement powders, except that X-ray microtomography is required to obtain sufficient spatial resolution to characterize the particles using spherical harmonics [Garboczi and Bullard 2004]. To obtain realistic cement particle shapes in the microstructure, mark the check box and select the shape set from the pull-down menu selector. **Note** that requesting realistic particle shapes will require significantly more time to create the microstructure, sometimes two or three times as long.

Note: If the real particle shape checkbox is not selected, then the cement particles all will be digitized spheres.

System size for the binder: The number of voxels in each linear dimension of the 3D grid can be chosen by the user, the default value being 100 in each direction. As already mentioned, each cubic voxel in the cement paste is 1 μm on a side, so the number of voxels in each dimension is numerically equal to the linear dimension. Note that larger values of the linear dimensions will require significantly more time to create the microstructure; the time required to create a microstructure scales linearly with the number of voxels N_{cp} in the grid, which can be calculated according to the equation

$$N_{cp} = N_x \times N_y \times N_z$$

where N_x , N_y , and N_z are the numbers of voxels in the cement paste in the x, y, and z directions of the grid.

System size for the concrete: This section appears only if fine or coarse aggregate is being added to create a mortar or concrete. The default values for the


Prepare Mix

linear dimensions and resolution are determined by the grading specified by the user. However, these values may be changed subject to the following constraints:

The minimum linear dimension of the concrete system must be at least twice as big as the opening of the coarsest sieve that retains any aggregate.

The resolution chosen from the pull-down menu selector must be no more than half the opening of the finest sieve that retains any aggregate.

These constraints are used to ensure that each aggregate particle in the grading fits into the box and can be approximately visualized in the packing. If either of these constraints is violated, an alert box will appear with a message describing which constraint was violated. Clicking the “OK” button on the dialog box dismisses it and also causes the offending dimension or resolution to be reset to an acceptable value that satisfies the constraints.



Note: Even when coarse or fine aggregates are included in the mix, the 3D aggregate packing is not created by default. To override this behavior and force the aggregate packing to be created, the checkbox next to “Create the 3D aggregate packing” must be checked.

Note: Creating a virtual aggregate packing often takes significant computational resources because the shapes are created individually from the spherical harmonic coefficients stored in the database. As with the cement paste system, the time required to create a 3D aggregate packing will scale linearly with the number of voxels N_{ap} in the aggregate packing, which can be calculated according to the equation:

$$N_{ap} = \frac{L_x \times L_y \times L_z}{\lambda^3}$$

where L_x , L_y , and L_z are the linear dimensions of the grid in mm, and λ is the resolution in mm/voxel.

Note: If fine or coarse aggregates are included in the mix, then a flat “slab” of aggregate will be inserted parallel to the yz plane in the center of the cement paste microstructure, regardless of whether or not an aggregate packing is requested. This aggregate slab is inserted to simulate the packing limitations of cement particles near an aggregate surface, the phenomena leading to the interfacial transition zone (ITZ) in mortar and concrete. The properties of the ITZ are important in determining the mechanical properties and transport properties of mortar and concrete [Bentz and Garboczi 1999b], so it is important that the ITZ be recreated in the virtual cement paste microstructure so that its properties can be subsequently computed and incorporated into calculations of mortar and concrete properties.

Prepare Mix

Saving the mix

The last steps in creating a mix are to give the mix a unique name (i.e. one that does not already exist in the database) and execute the mix creation program. Type a name for the mix in the text box provided. Names can include upper case or lower case letters, numbers, or spaces. After typing the proposed name and clicking anywhere outside the text box, the software will validate the name. A green checkmark next to the name indicates that it is valid.

File name:   Notes: 

On the other hand, a red X indicates that the name has already been used for an existing mix.

You already have a mix with the same name.

File name:   Notes: 

Once a valid name has been chosen, click on the “Create the mix” button to begin creating the mix. The status of the mix operation can be checked on the “My Operations” page, as described in detail in [Section 9](#).

7.2 Hydrate Mix

The NIST cement hydration model [Bentz 1997, Bentz 2005] operates directly on 3D digital images of cement paste microstructures created as described earlier. Execution of the model requires a starting microstructure, information about the curing conditions (thermal conditions and moisture state), and the frequency at which to output various data for later analysis.

To begin hydrating a mix, first select the mix name from the pull-down menu selector. This is the name chosen when the mix was created. In addition, at this point you may specify the apparent activation energies of the three major “net” hydration processes that can occur: (1) cement hydration, (2) pozzolanic reactions,

1. Prepare Mix 2. Hydrate Mix

Step 2: Hydrate my mix ?

Mix properties ?

Choose a mix: Cement140-Mortar

▼ Reaction activation energies

Cement hydration: 40.0 kJ/mole

Pozzolanic reactions: 83.14 kJ/mole

Slag reactions: 50.0 kJ/mole

including fly ash hydration and silica fume reactions and (3) slag hydration. The default values that are provided reflect sensible values based on a survey of the literature (for example, see ASTM C 1074 [ASTM 2008]). The section for modifying the activation energies is collapsed when the page first opens, but may be expanded by clicking on the small grey triangle next to the heading “Reaction activation energies”.

Thermal conditions

The thermal condition of the hydrating material may be (1) isothermal, (2) semi-adiabatic, or (3) adiabatic.

Thermal conditions

isothermal

semi-adiabatic

adiabatic

Initial temperature: 25.0 °C

My Operations

Isothermal: The material is in diathermal contact with a constant-temperature reservoir and heat transfer is sufficiently rapid to maintain the material at the temperature of the reservoir. The default value is 25 °C.

Thermal conditions

isothermal
 semi-adiabatic
 adiabatic

Initial temperature: °C
Ambient temperature: °C
Heat transfer coefficient:

Semi-adiabatic: Heat generated by hydration reactions is transferred to a surrounding reservoir that is at a fixed temperature, but the transfer rate is slow enough that some of the generated heat causes the material temperature to increase. If this option is selected, then not only the initial temperature of the material must be specified (default 25 °C), but also the temperature of the surrounding reservoir (default 25 °C) and the effective heat transfer coefficient, in units of W/K (default 10.0).

Adiabatic: The material is perfectly insulated from its environment, so all the heat generated by hydration reactions is used to increase the temperature of the material. If this option is chosen, only the initial temperature of the material must be specified. The default value is again 25 °C.

Aging

This section is used to specify the total length of time that the material should be hydrated. The time is specified by entering the desired number of days in the text box provided or, alternatively, by specifying a maximum degree of hydration at which the simulation will terminate.

- Aging ?

Hydrate for days
... Or stop at degree of hydration:

Time conversion factor h/cycle²

The other required element is the “time conversion factor”, which has units of h/cycle². The NIST hydration model proceeds in repeated “cycles” of dissolution, diffusion, and reaction. These cycles have no intrinsic time scale, so one must define an assumed relationship between time (in hours) and computational cycles. In the current version of eVCCTL, hydration time, t , in hours is related to the number of computational cycles, n , according to the parabolic relation

My Operations


$$t = \beta n^2$$

where β is a time conversion factor that must be specified. The default value of 3.5×10^{-4} is a value that works reasonably well for a number of cements, but which is not optimized to any particular cement. To optimize the time conversion parameter, a calibration of the model against some experimental measure of the degree of hydration, chemical shrinkage, or isothermal heat release should be made.

Note: The parabolic relation employed for the time scale is not used for any fundamental reason, but only because it often provides a reasonable fit to experimental measurements of the progress of hydration with time, provided that the time conversion factor is calibrated sufficiently well.

Saturation conditions

The two moisture condition options are saturated or sealed. The saturated condition means that the cement paste is in contact with a reservoir of excess water. As free water in the capillary pores is consumed by the hydration reactions, it is immediately replaced by water from the reservoir. Note, however, that once the capillary porosity reaches its percolation threshold and becomes disconnected,



water replacement is no longer possible even under saturated conditions. The sealed condition means that free water consumed during hydration is not replaced. Instead, the capillary pores are progressively emptied of water, starting in those pore regions with the largest effective diameters.

Simulation parameters

This section is collapsed when the page first opens because it will not usually be of interest. It can be expanded by clicking on the small grey triangle next to the heading. The only simulation parameter that can be modified in eVCCTL is the value of the seed for the random number generator. See the discussion on [random number seeds](#) in [Section 7.1](#) for a description.

Data output

This section is collapsed when the page first opens. It can be expanded by clicking on the small grey triangle next to the heading. This section can be used to specify how frequently (in hours of simulated age) the hydration model will output certain properties to data files.


Evaluate percolation of porosity ... Percolation properties like this one tend to consume significant computational time to calculate because the calculations

My Operations

involve nested iterations over most or all of the system voxels. Therefore, it is recommended that percolation properties not be evaluated any more often than necessary. The percolation state of the capillary porosity determines the point at which water can no longer be absorbed from an external source to maintain saturated conditions. Once the hydration model detects that the pore space is depercolated, this calculation will no longer be made no matter what value is typed into the text box. The default value is 1.0 h.

Evaluate percolation of total solids ... This property provides an indication of initial setting time, so it should be evaluated fairly frequently to obtain a reasonable assessment of setting time of a material. The default value is 0.5 h.

Output hydrating microstructure ... The state of the entire 3D microstructure can be saved at regular intervals during the hydration process. Subsequent calculations of the linear elastic moduli, compressive strength, and transport properties of the material at a particular state of hydration can only be made if the microstructure is available at that state. The default value is 72.0 h.



The screenshot shows a control panel titled "Data output" with a dropdown arrow and a help icon. It contains three input fields for evaluation intervals in hours: "Evaluate percolation of porosity every: 1.0 hours", "Evaluate percolation of total solids every: 0.5 hours", and "Output hydrating microstructure every: 72.0 hours". Below these fields is a "File name:" label followed by a text box containing "HydrationOf-Cement140-Mortar". At the bottom of the panel is a button labeled "Hydrate the mix".

Executing the hydration simulation

To execute the simulated hydration operation, provide a unique name for the operation in the box next to "File name" at the bottom of the page. The default name is the name of the mix with the prefix "HydrationOf-" prepended. The default name can be modified, but must be unique. The software validates the name before and will indicate a green ✓ (okay) or a red ✗ (invalid) next to the name. Once a valid name is selected, click on the "Hydrate the mix" button to launch the operation. The status of the hydration operation can be checked on the "My Operations" page, as described in detail in [Section 9](#).

Note: One or more hydration operations for a particular mix can be requested and launched even before the mix operation has been completed. If the mix operation is still running when the hydration request is made, a message will appear saying,

"The mix you want to hydrate is not ready now. The hydration will begin as soon as the mix preparation is finished".

In other words, the hydration operation is queued to run as soon as the mix operation completes and a starting microstructure is available.

8 Measurements

In eVCCTL, there are 61 properties that are continuously tracked during a hydration operation, and all of them are stored in a data file that can be accessed for online plotting or exporting to a spreadsheet for further analysis. See [Appendix II](#) for a listing of all the available “hydrated properties”. In addition, the linear elastic moduli, compressive strength and transport properties of cement pastes, mortars, or concretes can be calculated on hydrated microstructures. The Measurements page provides access to all these virtual measurement capabilities.


Clicking on the “Measurements” tab of the main menu bar opens a page with a submenu having two options: (1) Plot Hydrated Properties, and (2) Measure Cement/Concrete Properties.

8.1 Plot Hydrated Properties

This page provides a flexible inline plotting capability for plotting the evolving properties of a hydrating material. To create a plot, first select the desired x-axis property from the pull-down menu selector. The default x-axis is “Time”, in hours, but any other hydrated property can be selected as well.

With the x-axis selected any number of properties can be simultaneously plotted on the y-axis, including multiple properties from a single hydration simulation, or a comparison of the same properties for different hydration simulations. To create a plot, first select a hydration operation on the left pull-down menu selector (under the heading “Hydration Name”), and then select the desired property to plot in the right pull-down menu selector (under the heading “Property”). Doing so will immediately create the xy plot in the “Plot result” section.

My Operations



The plot is accompanied by a legend indicating both the hydration operation and the property, separated by a colon.

Click the “+” button next to the first property in the “Set axes” section to plot a second property on the same plot. This will create a second row with the same pull down menus repeated. The example shown below plots both the degree of hydration and total capillary porosity against time for the same hydration operation. Notice that the legend is updated to display the information for each curve in the plot.

Note: When plotting multiple properties on the same graph, the properties must all have commensurate units. For example, both the degree of hydration and the total porosity are dimensionless quantities, so they can be plotted together. However, the degree of hydration and isothermal heat release have different units, so they cannot be plotted simultaneously. The pull-down menu selectors automatically exclude incommensurate properties.


You can also compare properties from different hydration operations to analyze differences in the behavior of the two systems. The following example adds to the example just given by plotting the degree of hydration for another hydration operation. Notice that the second hydration operation, “HydrationOf-ASTMC109-02” only ran for 24 hours.

Plotted curves can also be removed from the graph by clicking on the “-” button next to the corresponding row in the “Set axes” section.

Note: Under some conditions, the generated plot may not automatically rescale its axes in an optimal way. This can be corrected by simply clicking once anywhere within the region of the plot itself.

It is also possible to zoom in on a narrow range of the x-axis. To do so, place the mouse within the plot field at the beginning x value. Hold the mouse button down and drag to the ending x value. Releasing the mouse will automatically generate the rescaled plot. Again, to go back to the optimal scaling needed to show all the data, just click once within the plot region.

My Operations



Finally, a high-resolution plot can be created in separate pop-up window by clicking on the “High resolution version” link below the legend. The same zooming features apply to the high-resolution plot as for the regular plot.

Note: When a hydration operation is running, its progress can be monitored by going to this plotting page. The default plot, which has time on the x-axis, will show how much simulation time has been reached, even if the operation has not completed.

8.2 Measure Cement/Concrete Properties

Clicking on this subtab opens a page for calculating the linear elastic properties, compressive strength, and the effective diffusivity of cement pastes, mortars, or concretes that have been hydrated. The desired hydration operation can be chosen from the pull-down menu selector. When this is done, a listing of the available hydration times for this operation appears under the heading “Properties”.

Recall that, when a hydration operation is requested, you have the option to select the time intervals at which to output the partially hydrated 3D microstructures. For example, if you chose 72.0 h for this interval, then

My Operations

microstructures were saved at approximately 72 h, 144 h, 216 h, etc. These are the same times that now appear in the list on this page, as individually collapsed sections, any of which can be expanded by clicking on the small grey triangles next to the headings.

Plot Hydrated Properties Measure Cement/Concrete Properties

Measure Cement or Concrete Properties ?

Choose the hydration result: HydrationOf-Cement140-Mortar ?

Properties ?

- ▶ After 144.3 hours hydration
- ▶ After 216.6 hours hydration
- ▶ After 288.7 hours hydration
- ▶ After 361.2 hours hydration
- ▶ After 433.6 hours hydration

When one of these individual sections is expanded, it reveals two buttons, one to calculate the elastic properties (effective linear elastic moduli) and one to calculate the transport properties (effective diffusivity). Clicking on these buttons launches the finite element models that calculate these properties on the digital image [[Garboczi 1998](#)].

▼ After 651.5 hours hydration

Elastic Properties

Measure Elastic Moduli

Transport Properties

Measure Transport Factor

The finite element calculations take significant computational time to complete, about 20 minutes to 30 minutes for a typical 100 x 100 x 100 grid. Once the calculations begin, the relevant section of this page will display several boxes that will eventually contain the results of the calculations. While the calculations are ongoing, however, these boxes will display the message “Measuring...”. The data that are displayed in these boxes when the calculations are completed is described now.

My Operations

▼ After 651.5 hours hydration

Elastic Properties

Measuring...

Measuring...

Measuring...

Measure Elastic Moduli

Transport Properties

Measuring...

Measure Transport Factor

Elastic Properties Results

There are three text boxes to display the elastic properties results:

- A summary of the effective elastic properties of the cement paste, including the bulk modulus, K in GPa, shear modulus, G in GPa, Young's modulus, E in GPa, and Poisson ratio, ν . If the material is a mortar or concrete, this box will also display the effective elastic properties of the mortar or concrete. These latter properties are calculated with Differential Effective Medium Theory (D-EMT) [[Garboczi and Berryman 2001](#)], and include the effective K , G , E , and ν . The D-EMT model takes the cement paste elastic properties, aggregate elastic properties, and the properties of the ITZ (also gleaned from the finite element calculations on the cement paste near the aggregate surface, as described below), as well as the volume fractions of the paste, aggregates, and air voids. In addition to these properties, a mortar or concrete will also have the estimated compressive strength displayed in the box, in MPa, which is estimated from the empirical relationship between Young's Modulus and compressive strength described by Neville [[Neville 1995](#)].
- The second box shows the relative contribution to the elastic properties of each phase in the microstructure. For each phase in turn, the following data are provided: (1) the volume fraction of the phase, (2) the mean value, over all the voxels of the given phase, of the bulk modulus

My Operations

calculated using the linear elastic relation between the local stress and the macroscopically applied strain, (3) the fraction that this value is of the total effective bulk modulus of the material; (4) and (5) are the same quantities calculated for the shear modulus; (6) and (7) are the same quantities calculated for the Young's modulus.

- The third box contains information about the variation of the elastic properties of the cement paste as a function of distance perpendicular to the aggregate surface. The data appear in five columns, identified here as (1) distance from the aggregate in μm , (2) K for the paste (GPa), (3) G for the paste (GPa), (4) E for the paste (GPa), and (5) ν for the paste. These data are calculated directly from the finite element model results and are used to determine the elastic properties of the ITZ. The ITZ properties are determined by averaging these data over thicknesses of the ITZ, which is approximately equal to the median particle size of the starting cement powder [[Bentz and Garboczi 1999b](#)].

Elastic Properties


CEMENT PASTE ELASTIC MODULI:				
	bulk_modulus	18.789102	GPa	
	shear_modulus	9.564258	GPa	
	Youngs_modulus	24.530503	GPa	
Phase POROSITY				
	Vfrac	0.170451		
	Bulk_Modulus	0.565594		
	Bulk_Modulus_Fraction	0.030102		
0.5	8.9923	4.5899	11.7676	0.2819
1.5	10.4965	5.3563	13.7330	0.2819
2.5	10.7687	5.6703	14.4710	0.2760
3.5	7.0693	4.7245	11.5914	0.2267
4.5	4.8923	3.5753	10.8910	0.2513

Measure Elastic Moduli

Transport Properties Results

Calculated transport properties are all displayed in one box, and consist of the relative diffusion coefficient in the x, y, and z directions. Here the relative diffusion coefficient is defined as the effective diffusion coefficient of mobile solution species in the material, divided by the diffusion coefficient of the same species in pure pore solution of the same composition. In addition, the average relative diffusion coefficient over all three dimensions and the formation factor are displayed in the text box. The formation factor is the inverse of the average relative diffusion coefficient as defined here.

My Operations



Following the value of the formation factor, the text box displays phase-specific information similar to that displayed for elastic properties above. . For each phase in turn, the following data are provided: (1) the volume fraction of the phase, (2) the relative conductivity of the phase, that is, the conductivity of mobile species through the phase itself divided by the conductivity of the same species through pure pore solution of the same composition; saturated porosity has a relative conductivity of 1.0 by definition, and solid dense phases have a relative conductivity of 0.0, (3) the fraction that this phase contributes to the overall effective conductivity of the composite materials in each orthogonal direction.

9 My Operations

The “My Operations” page is the central location for checking the status of a user’s operations. This guide has already discussed all of the major operations that can be executed in eVCCTL, but now is a good time to list all the types in summary.

Microstructure: Creation of a cement paste microstructure

Aggregate: Creation of a mortar or concrete aggregate packing

Hydration: Simulating the hydration of a cement paste

Elastic-moduli: Calculation of elastic moduli of a cement paste, mortar, or concrete

Transport-factor: Calculation of relative diffusion coefficients and formation factor

On the “My Operations” page, each operation for a user is listed in one of four sections, depending on their status: queued, running, finished, or canceled.

Queued operations

When an operation is requested on one of the eVCCTL pages, it is given an entry in the database and is placed in a queue waiting to be run. Some operations will leave the queue and begin running almost immediately, but some others, such as hydration operations waiting for their microstructure to be created, will remain in the queue for some time. While in the queue, a new directory is created to store the

My Operations

results, and an input file is created for the C program that will process the input and generate the results. On the “My Operations” page, operations in the queue appear in a yellow table at the top of the page, with information about the type of operation

Queued operations

Name	Type	Time queued	
HydrationOf-Cement140-Paste	Hydration	16 May 2010 22:13:38	Delete

(see the previously enumerated list for types) and the time of the request displayed.

At the right of the entry is a link to delete the operation from the queue.

Clicking on the “Delete” link will remove the operation request from the database and delete the directory associated with the operation.s

Running operations

While an operation is running, it appears in a green table in this section. The name of the operation appears as a link. If the name is clicked, the “My Files” page is opened to the operation in question so the user can examine the files that have been generated for the operation. See [Section 10](#) for more detail on the “My Files” page. In addition to the name, the operation type and the time started are displayed.

Name	Type	Time started	
Cement140-Paste	Microstructure	16 May 2010 22:13:32	Cancel

At the right of the entry is a link to cancel the operation. Clicking on the “Cancel” link will terminate the C program that is running the operation, and the operation will be moved to the “Canceled operations” section of the page. The input and output files associated with the operation will remain intact.

Finished operations

When the C program responsible for running an operation has finished (either successfully or unsuccessfully), the operation is moved from the “Running operations” section to this section. It appears as an entry in a blue table. As before, the name of the operation appears as a link that redirects the page to the operation’s entry in the “My Files” page. In addition to the name, the operation type is displayed, as well as the time the operation started and finished.

At the right of each entry is a link to delete the finished operation. Clicking on the “Delete” link will remove the operation’s listing from the database. All input and output files associated with the operation also will be removed from the computer.

Note: The deletion of an operation cannot be undone, so use this feature with caution.

My Operations

Name	Type	Time started	Time finished	
HydrationOf-Cement152-Mortar/Transport-factor-9	Transport-factor	16 May 2010 20:08:12	16 May 2010 20:11:05	Delete
HydrationOf-Cement152-Mortar/Elastic-moduli-9	Elastic-moduli	16 May 2010 20:08:07	16 May 2010 20:43:34	Delete

Canceled operations

If a running operation is canceled, its entry appears in this pink table. In eVCCTL, the operation cannot be restarted, but it can be deleted. Clicking on the “Delete” link at the right of the entry will remove the operation’s listing from the database and will also remove all input and output files associated with the operation from the computer. The deletion of a canceled operation cannot be undone.

Name	Type	Time started	Time cancelled	
Cement140-Paste	Microstructure	16 May 2010 22:13:32	16 May 2010 22:15:02	Delete

10 My Files

Other than the “Measurements” page, the “My Files” page is the main location for viewing the progress and results of an operation. The input and output files associated with an operation can be viewed here or optionally exported to the computer’s Desktop for further examination.

The “My Files” page has five sections, one for each type of operation (see the enumerated list at the beginning of [Section 9](#) for a listing of the operation types). Each of these sections displays the name of every operation of that type that is recorded in the database, regardless of whether the operation is queued, running, finished, or canceled. Deleted operations do not appear.

The name of a given operation is actually the heading of a collapsed field that can be expanded by clicking on the small grey triangle next to the operation name. Expanding a section reveals a three-column table listing all the input and output files associated with the operation, along with a short description of the file contents and options for viewing or exporting the file. A link appears at the end of each table to export all of the files at once in a single compressed archive to your Desktop or Downloads folder.

10.1 Microstructure Operations

Finished microstructure operations have seven or eight associated files, each of which is briefly described here.

- ▼ Cement152-Mortar

File	Description	Content
ASTM-C109.gdg	Grading	Show Export
Cement152-Mortar.bias	One-pixel bias numbers	Show Export
Cement152-Mortar.img	Microstructure image	Show Export
Cement152-Mortar.img.in	Input to genmic	Show Export
Cement152-Mortar.img.out	Output from genmic	Show Export
Cement152-Mortar.img.struct	Particle SH coefficients	Show Export
Cement152-Mortar.pimg	Particle image file	Show Export
Cement152-Mortar.stt	Cement phase statistics	Show Export

Export all files for this operation in one zip file: [Cement152-Mortar.zip](#)

Grading: A text file containing the aggregate grading specified when creating a mortar or concrete. This entry will not be present for cement pastes. The contents of this file, and any other simple text file, can be displayed in a scrolling text box by clicking on the “Show” link at the right of the entry. It consists of three columns: (1) the common name of the sieve, (2) the sieve opening size (in mm), and (3) the mass fraction of aggregate retained in the sieve. The text box can be hidden again by clicking on the “Hide” link. Of course, this or any other file on the “My Files” page can be exported to the Desktop or Downloads folder by clicking on the “Export” link.

- ▼ Cement152-Mortar

File	Description	Content															
ASTM-C109.gdg	Grading	<div style="border: 1px solid #ccc; padding: 5px;"> Hide Export <table style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="text-align: left;">Sieve</th> <th style="text-align: left;">Diam</th> <th style="text-align: left;">Mass_frac</th> </tr> </thead> <tbody> <tr> <td>No. 5</td> <td>4.000</td> <td>0.0</td> </tr> <tr> <td>No. 6</td> <td>3.350</td> <td>0.0</td> </tr> <tr> <td>No. 7</td> <td>2.800</td> <td>0.0</td> </tr> <tr> <td>No. 8</td> <td>2.360</td> <td>0.0</td> </tr> </tbody> </table> </div>	Sieve	Diam	Mass_frac	No. 5	4.000	0.0	No. 6	3.350	0.0	No. 7	2.800	0.0	No. 8	2.360	0.0
Sieve	Diam	Mass_frac															
No. 5	4.000	0.0															
No. 6	3.350	0.0															
No. 7	2.800	0.0															
No. 8	2.360	0.0															
Cement152-Mortar.bias	One-pixel bias numbers	Show Export															

One-pixel bias numbers: Cement paste microstructures in eVCCTL have a resolution of 1 μm , but a large number of cement particles are smaller than this minimum feature size. To include these particles in the virtual microstructure, they are represented as 1 μm clusters of smaller particles. These clusters should have a higher surface area and, consequently, a greater rate of reaction with water than a single particle of the same size. The one-pixel bias numbers, calculated from knowledge of the cement particle size distribution in the submicrometer range, are included in this file as a triplet of numbers, one number on each row, for each phase in the initial microstructure. The triplet is formatted as follows:

The first number in the triplet is always 0, for reasons having to do with the legacy versions of the software.

The second number in the triplet is the bias value, a decimal number typically near 1.0, but which may be significantly greater than 1.0 for fine cements, or slightly less than 1.0 for coarse cements.

The third number in the triplet is the integer identification number of the phase. [Appendix I](#) lists the identification numbers for the phases.

Microstructure image: This file contains a listing of the phase occupying each voxel in the 3D virtual microstructure. The file has a five-line header with self-descriptive entries, followed by the integer phase identification number for each voxel in the grid, with one voxel per row. Ordinarily, the text version of this file will hold little interest to the user. Therefore, clicking on the “Show” link will cause a thumbnail color image of a 2D slice from the microstructure to display. Please refer to [Section 10.2](#) for more information on working with these images.

Input to genmic: This is the input file read by the C program (`genmic`) that creates the virtual microstructure. It is difficult to read because it is not annotated in any way. More sense can be made of the input file by viewing it in conjunction with the output file, the latter which provides a running commentary on the types of input being read.

Output from genmic: This is the output file produced by the C program (`genmic`) as it runs, especially describing the nature of the input values that are read. **Note:** Ordinarily, the output file will be of little interest, but it can provide important clues to the cause of any failure of the program to execute properly. If `genmic` fails for some reason, an error message will typically appear near the end of the output file.

Particle SH coefficients: A listing of the coefficients in the spherical harmonic (SH) expansion describing the shape of each particle in the microstructure. This file probably is of no interest to users of eVCCTL.

Particle image file: This file is a complement to the microstructure image file. Whereas the microstructure image associates a unique phase identification number to each voxel, the particle image file associates a particle number to each voxel. Specifically, a voxel is assigned a number n if the phase at that voxel belongs to the n th particle in the microstructure. Porosity is assigned the number zero, and particles comprised of only one voxel also are assigned zero. This file is used

My Operations


internally by the C program responsible for hydration operations (`disrealnew`) and should hold no interest for users of `eVCCTL`.

Cement phase statistics: A tabular display of the number of voxels assigned to each phase in the final microstructure, along with the corresponding mass fraction, volume fraction, and surface area fraction of that phase in the virtual microstructure. This file consists of two sections. The first eight lines of the file display the phase statistics on a total clinker solid basis. This section can be used to determine how closely the final microstructure reproduces the clinker phase fractions and w/b ratio that were requested when the operation was launched. The remaining part of the file lists four values for each phase

- The number of voxels assigned to that phase
- The number of voxel **faces** of that phase that are adjacent to porosity; this is the digitized analog of the surface area.
- The volume fraction of the phase in the microstructure, on a total volume basis (solids plus porosity)
- The mass fraction of the phase in the microstructure, on a total mass basis (solids plus porosity)

10.2 Displaying Microstructure Images

As already described, microstructure images are displayed as color 2D slices of the 3D microstructure. `eVCCTL` provides the ability to view the microstructure at different magnifications and from different perspectives, so we now devote attention to explaining these features.




Clicking on the “Show” link for any microstructure image file displays a thumbnail image of a 2D cross section from the 3D virtual microstructure. Note that it may take several seconds for this image to display because it is being created at the time of the “Show” request.

The thumbnail is a color image, with each color corresponding to a different phase in the mix. A red vertical stripe through the center of the image represents a flat “slab” of aggregate, which is necessary for simulating the packing effects in the ITZ, as mentioned in an earlier section. The aggregate slab will be present only if coarse or fine aggregate was requested in the mix.

Once the thumbnail is displayed, it can be clicked with the mouse to open another page for more detailed examination and manipulation of the image.

My Operations

Image Name: Cement152-Mortar.img.3.50.x3.png Plane to view: Slice to view: Magnification: X



Legend



C₃S



C₂S



C₃A



C₄AF



K₂SO₄



Na₂SO₄



Gypsum



Hemihydrate



Plane to view: Choose one of three orthogonal directions from which to view the microstructure. The viewing planes are defined by the two Cartesian coordinate axes they contain (e.g., the yz plane is the plane observed when viewing along the x-axis).

Slice to view: Changing this value enables the user to view the image at different locations along the axis of viewing. Valid values are in the interval $[0, L_x - 1]$, where L_x is the number of voxels in the direction being viewed. Values outside the valid interval are converted to the nearest value in the valid interval. For example, a slice value of -7 would be converted to 0.

Magnification: A positive integer value of M displays the image with $M \times M$ image pixels corresponding to each voxel in the microstructure. Note: the magnification value must be a positive integer. A non-integer value will throw an error.

Once the viewing options are selected, click on the “Get image” button or just press the Enter key on the keyboard to view the new image. Images previously viewed while this page has been open can be accessed by clicking the “Back” button on your browser. Continued clicking of the browser’s “Back” button will return to the “My Files” page.

Underneath the displayed image is a key showing the colors assigned to each phase in the microstructure. The color key is quite similar to that used to view cements on the “Lab Materials” page, described in [Section 6.1](#).

10.3 Aggregate Operations

Finished aggregate packing operations have seven associated files, each of which is briefly described here.

– ▼ Cement152-Mortar/AggregateFiles

File	Description	Content
aggpack.in	Input to genaggpack	Show Export
aggpack.out	Output from genaggpack	Show Export
Aggregate.img	Microstructure image	Show Export
Aggregate.img.struct	Particle SH coefficients	Show Export
Aggregate.stt	Cement phase statistics	Show Export
oneimage.input		Show Export
oneimage.output		Show Export

Export all files for this operation in one zip file: [AggregateFiles.zip](#)

Input to genaggpack: This is the input file read by the C program (`genaggpack`) that creates the virtual microstructure. It is difficult to read because it is not annotated in any way. More sense can be made of the input file by viewing it in conjunction with the output file, the latter which provides a running commentary on the types of input being read.

Output from genaggpack: This is the output file produced by the C program (`genaggpack`) as it runs, especially describing the nature of the input values that are read. **Note:** Ordinarily, the output file will be of little interest, but it can provide important clues to the cause of any failure of the program to execute properly. If `genaggpack` fails for some reason, an error message will typically appear near the end of the output file.

Microstructure image: This file contains a listing of the phase occupying each voxel in the 3D virtual microstructure. In contrast to cement paste microstructures, an aggregate packing has either two or three phases present. Porosity and aggregate are always present. In addition, if the resolution of the packing is sufficiently fine that the ITZ can be resolved, it will appear as a separate phase for easy visualization. Clicking on the “Show” link will cause a thumbnail color image of a 2D slice from the microstructure to display. Please refer to [Section 10.2](#) for more information on working with these images.

Particle SH coefficients: A listing of the coefficients in the spherical harmonic (SH) expansion describing the shape of each particle in the packing. This file is of no immediate interest to users of `eVCCTL`.

Phase statistics: A tabular display of the number of voxels assigned to each phase in the final packing. There is one line for porosity, one line for aggregate, and

one line for ITZ. A value of zero for ITZ does not mean that there is no ITZ in the mortar or concrete, but instead means that the virtual packing was created at too coarse a resolution to include the ITZ in the image.

Besides these five files, a “oneimage.input” file and a “oneimage.output” file are also present in the table. These are used in the auxiliary program to render the aggregate packing image, and are of no interest to eVCCTL users.

10.4 Hydration Operations

Finished hydration operations often have a dozen or more associated files.

Cement alkali characteristics: Contains information on both the total and the readily-soluble potassium and sodium in the cement. The format and viewing of this file were discussed in [Section 6.1](#).

Fly ash alkali characteristics: This file is required even if the material does not contain any fly ash. Its format is identical to that for the cement alkali characteristics file.

Hydration image: There will likely be 10 or more of this type of file in the list. Each one is a saved 3D microstructure at a different time during hydration. The actual number of this type of file depends on the time interval that was specified between successive outputs and on the total simulated time. For example, if a user requests hydration for 28 d (672 h) with microstructure output every 72 h, there will be 10 hydration images (72 h, 144 h, 216 h, 288 h, 360 h, 432 h, 504 h, 576 h, 648 h, and a final microstructure at 672 h when the run finishes). All but the final hydration image files has the following pattern for its name

MicrostructureName.img.xxx.xxh.TT.0yz

where

- MicrostructureName is the name given to the initial microstructure (i.e. the microstructure operation name)
- xxx.xxh is the number of hours (to the nearest 0.01 h) of hydration to which this image corresponds. **Note:** The exact time at which the microstructure is output is as close to the desired time interval as possible, but the elapsed time of each hydration cycle is not constant and so output at the exact time interval requested is rarely possible.
- TT is the initial temperature used for the hydration operation, in degrees Celsius
- y is 0 if isothermal conditions were specified, or is 1 if adiabatic or semi-adiabatic conditions were specified
- z is 0 if hydrating under saturated conditions, or is 1 if hydrating under sealed conditions.

My Operations

▼ HydrationOf-Cement152-Mortar

File	Description	Content
alkalichar.dat	Cement alkali characteristics	Show Export
alkalifyash.dat	Fly ash alkali characteristics	Show Export
Cement152-Mortar.img.144.26h.25.001	Hydration image	Show Export
Cement152-Mortar.img.216.78h.25.001	Hydration image	Show Export
Cement152-Mortar.img.289.20h.25.001	Hydration image	Show Export
Cement152-Mortar.img.361.29h.25.001	Hydration image	Show Export
Cement152-Mortar.img.433.57h.25.001	Hydration image	Show Export
Cement152-Mortar.img.505.68h.25.001	Hydration image	Show Export
Cement152-Mortar.img.577.93h.25.001	Hydration image	Show Export
Cement152-Mortar.img.650.22h.25.001	Hydration image	Show Export
Cement152-Mortar.img.72.14h.25.001	Hydration image	Show Export
HydrationOf-Cement152-Mortar.data	Hydration results	Show Export
HydrationOf-Cement152-Mortar.hyd.in	Input to disrealnew	Show Export
HydrationOf-Cement152-Mortar.hyd.out	Output from disrealnew	Show Export
HydrationOf-Cement152-Mortar.img.25.001	Hydration image	Show Export
image_index.txt		Show Export
parameter_file.prm	Parameters file	Show Export
slagchar.dat	Slag characteristics	Show Export

Export all files for this operation in one zip file: [HydrationOf-Cement152-Mortar.zip](#)

As an example, a hydrated image name of `MyMic.img.289.20h.25.001` means the original microstructure is named `MyMic.img`, the microstructure was output at 289.20 h of hydration time, the initial temperature was 25 °C, and isothermal and saturated conditions were used.

The exception to this naming pattern is the final image that is written when the hydration operation terminates. This final image has the pattern

$$\text{HydrationName.img.TT.0yz}$$

where

- `HydrationName` is the name given to the hydration operation when it was launched. It should be the same as the heading for the table
- `TT` is the initial temperature used for the hydration operation, in degrees Celsius
- `y` is 0 if isothermal conditions were specified, or is 1 if adiabatic or semi-adiabatic conditions were specified
- `z` is 0 if hydrating under saturated conditions, or is 1 if hydrating under sealed conditions.

My Operations

For any of the hydration images, clicking on the “Show” link will cause a thumbnail color image of a 2D slice from the microstructure to display. Please refer to [Section 10.2](#) for more information on working with these images.

Input to disrealnew: This is the input file read by the C program (disrealnew) that performs the virtual hydration operation. It is difficult to read because it is not annotated in any way. More sense can be made of the input file by viewing it in conjunction with the output file, the latter which provides a running commentary on the types of input being read.

Output from disrealnew: This is the output file produced by the C program (disrealnew) as it runs, especially describing the nature of the input values that are read. **Note:** Ordinarily, the output file will be of little interest, but it can provide important clues to the cause of any failure of the program to execute properly. If disrealnew fails for some reason, an error message will typically appear near the end of the output file.

Image_index.txt: This is a two-column text file. The left column gives the times at which the hydration images were output, and the right column contains the full path name to the hydration image in question. Ordinarily, this file will be of no interest to the user, because any or all the images can be exported to the Desktop or Downloads folder by clicking on the “Export” link.

Parameters file: A listing of the several dozen parameters used by the C program (disrealnew) in its execution. These parameters cannot be modified by the user.

Slag characteristics: Contains information the physical and chemical characteristics of the slag, and the slag hydration products, used in the microstructure. This file must be input to the hydration operation even if no slag is present in the microstructure. The format and viewing of this file were discussed in [Section 6.2](#).

Hydration Results: A large tabular display of the values of the 61 hydration properties at each computational cycle. This file has 63 columns and several hundred rows, making it difficult to view in the small text box that is provided when the “Show” button is clicked. It is much more convenient to Export the file to the Desktop and then import the table into a spreadsheet application. Also, recall that any one or more of the properties in this file can be simultaneously plotted on the Measurements page of eVCCTL.

The meaning of each of the 63 columns in the hydration results file is provided in [Appendix II](#).

10.5 Mechanical properties operations

Finished mechanical properties operations have five associated files, each of which is briefly described here.

My Operations

▼ HydrationOf-Cement152-Mortar/Elastic-moduli-9

File	Description	Content
EffectiveModuli.dat	Effective moduli results	Show Export
elastic.in	Input to elastic	Show Export
elastic.out	Output from elastic	Show Export
ITZmoduli.dat	ITZ elastic characteristics	Show Export
PhaseContributions.dat	Phase contributions	Show Export

Export all files for this operation in one zip file: [Elastic-moduli-9.zip](#)

Input to elastic: This is the input file read by the C program (`elastic`) that performs both the finite element calculations of the effective elastic moduli of cement paste and, for mortar or concrete, the effective medium theory calculations of the effective moduli and compressive strength of the material. This file has only a few lines, but it is not easy to understand because it is not annotated. More sense can be made of the input file by viewing it in conjunction with the output file, the latter which provides a running commentary on the types of input being read.

Output from elastic: This is the output file produced by the C program (`elastic`) as it runs, especially describing the nature of the input values that are read. **Note:** Ordinarily, the output file will be of little interest, but it can provide important clues to the cause of any failure of the program to execute properly. If `elastic` fails for some reason, an error message will typically appear near the end of the output file.

Effective moduli results: This file is displayed in the first text box on the Measurements page when a mechanical property operation is finished. Its format is described in [Section 8.2](#).

Phase contributions: This file is displayed in the second text box on the Measurements page when a mechanical property operation is finished. Its format is described in [Section 8.2](#).

ITZ elastic characteristics: This file is present only if aggregate has been included in the mix (i.e., only for a mortar or concrete). It is displayed in the third text box on the Measurements page when a mechanical property operation is finished. Its format is described in [Section 8.2](#).

10.6 Transport properties operations

Finished transport properties operations have four associated files, each of which is briefly described here.

Input to dc3d: This is the input file read by the C program (`dc3d`) that performs both the finite difference calculations of the effective relative diffusion coefficients and formation factor of the given microstructure image. This file has

My Operations

- ▼ HydrationOf-Cement152-Mortar/Transport-factor-9

File	Description	Content
dc3d.in	Input to dc3d	Show Export
dc3d.out	Output from dc3d	Show Export
TransportFactorOutput.dat	Major transport output data	Show Export
TransportFactorResults.dat	Transport factor results	Show Export

Export all files for this operation in one zip file: [Transport-factor-9.zip](#)

only a few lines, but it is not easy to understand because it is not annotated. More sense can be made of the input file by viewing it in conjunction with the output file, the latter which provides a running commentary on the types of input being read.

Output from dc3d: This is the output file produced by the C program (dc3d) as it runs, especially describing the nature of the input values that are read. **Note:** Ordinarily, the output file will be of little interest, but it can provide important clues to the cause of any failure of the program to execute properly. If dc3d fails for some reason, an error message will typically appear near the end of the output file.

Major transport output data: This file contains rather verbose output from the dc3d program, including the status of the conjugate gradient relaxation method [Garboczi 1998] at the end of each iteration. Ordinarily, this file will hold no interest for the user.

Transport factor results: This file is displayed in the text box on the Measurements page when a transport property operation is finished. Its format is described in [Section 8.2](#).

11 Logout

To gracefully log out of the eVCCTL system, click on the “Logout” tab in the main menu bar. This logs you out immediately and also takes you to the original login page for the system, where you can switch to a new user.

Note: If you wish to shut down eVCCTL and close the browser, as explained in [Section 3.1](#), you must also

- Wait for all running operations to finish, or cancel all running operations
- Close the web browser
- Open the Java console window and press `Ctrl-C`. After a brief pause, you will be asked, “Terminate batch job (Y/N)?”. Type “y” and press the Enter button. The Java console window will close.

12 Appendix I

This appendix gives the integer identification number and the short display name that is used in eVCCTL for each phase that is recognized in the system.

Phase Name	Display Name	ID
Saturated porosity	POROSITY	0
C ₃ S (alite)	C3S	1
C ₂ S (belite)	C2S	2
C ₃ A (cubic tricalcium aluminate)	C3A	3
C ₄ AF (tetracalcium aluminoferrite)	C4AF	4
K ₂ SO ₄ (arcanite)	K2SO4	5
Na ₂ SO ₄ (thenardite)	NA2SO4	6
CaSO ₄ ·2 H ₂ O (gypsum)	GYP SUM	7
CaSO ₄ ·0.5 H ₂ O (hemihydrate or bassanite)	HEMIHYD	8
CaSO ₄ (anhydrite)	ANHYDRITE	9
Silica fume	SFUME	10
Inert filler material	INERT	11
Slag	SLAG	12
Aggregate	INERTAGG	13
Aluminosilicate glass (in fly ash)	ASG	14
Calcium aluminosilicate glass (in fly ash)	CAS2	15
Amorphous silica (SiO ₂ in fly ash)	AMSIL	16
C ₃ A (in fly ash)	FAC3A	17
CH (calcium hydroxide or portlandite)	CH	19
C-S-H gel	CSH	20
C ₃ AH ₆ (hydrogarnet)	C3AH6	21
AFt (generic ettringite)	ETTR	22
AFt formed from C ₄ AF dissolution	ETTRC4AF	23
AFm (generic monosulfate)	AFM	24
FH ₃	FH3	25
C-S-H formed from pozzolanic reactions	POZZCSH	26
C-S-H formed from slag reactions	SLAGCSH	27
CaCl ₂	CACL2	28
C ₃ A·CaCl ₂ ·10 H ₂ O (Friedel's salt)	FRIEDEL	29
C ₂ ASH ₈ (strätlingite)	STRAT	30
CaSO ₄ ·2 H ₂ O (secondary gypsum)	GYP SUMS	31
CaSO ₄ ·2 H ₂ O (absorbed gypsum; not used)	ABSGYP SUM	32

My Operations

Phase Name	Display Name	ID
CaCO ₃ (calcite or aragonite or limestone)	CACO3	33
Calcium monocarboaluminate	AFMC	34
Mg(OH) ₂ (brucite)	BRUCITE	35
MgSO ₄	MS	36
CaO (free lime)	FREELIME	37
C ₃ A-o (orthorhombic C ₃ A)	OC3A	38
Empty porosity resulting from drying (not used)	DRIEDP	53
Empty porosity from self-desiccation	EMPTYP	55
Saturated porosity in a microcrack (not used)	CRACKP	56

13 Appendix II

This appendix provides a brief description of each column in the hydration results file (ending in .data; see [Section 10.4](#) for more information)

Column	Heading	Description
1	Cycle	The computational cycle
2	time(h)	The hydration time in hours
3	Alpha_mass	Degree of hydration on a cement mass basis
4	Alpha_fa_mass	Degree of hydration of fly ash on a fly ash mass basis
5	Heat(kj/kg_solid)	Heat produced (> 0 for exothermic, kJ/kg of solids)
6	Temperature(C)	Temperature of the system in degrees Celsius
7	Gsratio	Paste gel-space ratio (see [Taylor 1997])
8	Wno(g/g)	Non-evaporable water content (g water/ g cement), on an unignited cement mass basis
9	Wni(g/g)	Non-evaporable water content (g water/ g cement), on an ignited cement mass
10	ChemShrink(mL/g)	Chemical shrinkage in mL/g of cement
11	pH	Estimated pH of the capillary pore solution
12	Conductivity	Estimated DC conductivity of the pore solution, in S/m
13	[Na+](M)	Estimated Na ⁺ concentration in solution, in mol/L
14	[K+](M)	Estimated K ⁺ concentration in solution, in mol/L
15	[Ca++](M)	Estimated Ca ⁺⁺ concentration in solution, in mol/L
16	[SO4--](M)	Estimated SO ₄ ⁻⁻ concentration in solution, in mol/L
17	{K+}	Estimated activity of K ⁺ in solution on a molal basis (dimensionless)
18	{Ca++}	Estimated activity of Ca ⁺⁺ in solution on a molal basis (dimensionless)
19	{OH-}	Estimated activity of OH ⁻ in solution on a molal basis (dimensionless)

Column	Heading	Description
20	{SO4--}	Estimated activity of SO ₄ ²⁻ in solution on a molal basis (dimensionless)
21	Vfpore	Volume fraction of capillary pores
22	Poreconnx	Fraction of capillary pore volume that forms a percolated network in the x direction
23	Poreconny	Fraction of capillary pore volume that forms a percolated network in the y direction
24	Poreconnz	Fraction of capillary pore volume that forms a percolated network in the z direction
25	Poreconnave	Arithmetic mean of the previous three columns
26	Solidconnx	Fraction of solids that form a percolated network in the x direction
27	Solidconny	Fraction of solids that form a percolated network in the y direction
28	Solidconnz	Fraction of solids that form a percolated network in the z direction
29	Solidconnave	Arithmetic mean of the previous three columns
30 - 63	Vfxxx	Volume fraction of phase xxx on a system volume basis, where xxx is the display name of the phase given in Appendix I .

14 Bibliography

[ASTM 2008] Annual Book of ASTM Standards, vol. 04.01, American Society for Testing and Materials, West Conshohocken, PA, 2008.

[Bentz 1997] D.P. Bentz, "Three-dimensional computer simulation of cement hydration and microstructure development," J. Am. Ceram. Soc., 80 (1997) 3-21. <http://concrete.nist.gov/monograph>, Part I, Chapter 4, Section 2.

[Bentz 2005] D.P. Bentz, "CEMHYD3D: a three-dimensional cement hydration and microstructural development modelling package. Version 3.0," NISTIR 7232, U.S. Department of Commerce, June 2005. <http://concrete.nist.gov/monograph>, Appendix I-2.

[Bentz and Conway 2001], D.P. Bentz, J.T. Conway, "Computer modeling of the replacement of 'coarse' cement particles by inert fillers in low w/c ratio concretes: hydration and strength," Cem. Concr. Res., 31 (2001) 503-506. <http://concrete.nist.gov/monograph>, Part I, Chapter 4, Section 10a.

[Bentz and Feng 2000], D.P. Bentz, X. Feng, C.J. Haecker, P.E. Stutzman, "Analysis of CCRL proficiency cements 135 and 136 using CEMHYD3D," NISTIR 6545, U.S. Department of Commerce, 2000 1663-1671. <http://concrete.nist.gov/monograph>, Part I, Chapter 4, Section 3.

[Bentz and Garboczi 1991] D.P. Bentz, E.J. Garboczi, "Simulation studies of the effects of mineral admixtures on the cement paste-aggregate interfacial zone," ACI Mater. J., 88 (1991) 518-529. <http://concrete.nist.gov/monograph>, Part I, Chapter 6, Section 2.

[Bentz and Garboczi 1999] D.P. Bentz, E.J. Garboczi, C.J. Haecker, O.M. Jensen, "Effects of cement particle size distribution on performance properties of cement-based materials," Cem. Concr. Res., 29 (1999) 1663-1671.

[Bentz and Garboczi 1999a] D.P. Bentz, E.J. Garboczi, "Effects of cement particle size distribution on early age autogenous strains and stresses in cement-based materials," Cem. Concr. Res., 29 (1999) 1663-1671. <http://concrete.nist.gov/monograph>, Appendix I-2.

[Bentz and Garboczi 1999b] D.P. Bentz, E.J. Garboczi, "Computer modelling of the interfacial transition zone microstructure and properties," in: M.G. Alexander, G. Arliguie, G. Ballivy, A. Bentur, J. Marchand (Eds.), Engineering and Transport Properties of the Interfacial Transition Zone in Cementitious Composites. RILEM Report No. 20, RILEM Publications, Cachan Cedex, France, 1999, pp. 349-385. <http://concrete.nist.gov/monograph>, Part I, Chapter 7, Section 15.

Bibliography

- [Bentz and Haecker 1999] D.P. Bentz, C.J. Haecker, "An argument for using coarse cements in high performance concretes," *Cem. Concr. Res.*, 29 (1999) 615-618. <http://concrete.nist.gov/monograph>, Part I, Chapter 5, Section 8.
- [Bentz and Jensen 2000] D.P. Bentz, O.M. Jensen, K.K. Hansen, J.F. Olesen, H. Stang, C.J. Haecker, "Influence of cement particles size distribution on early age autogenous strains and stresses in cement-based materials," *J. Am. Ceram. Soc.*, 84 (2000) 129-135. <http://concrete.nist.gov/monograph>, Part I, Chapter 8, Section 2.
- [Bentz and Stutzman 1994] D.P. Bentz, P.E. Stutzman, "SEM analysis and computer modelling of hydration of portland cement particles," in: S.M. DeHayes, D. Stark (Eds.), *Petrography of Cementitious Materials*, American Society for Testing and Materials, Philadelphia, PA, 1994, pp. 60-73. <http://concrete.nist.gov/monograph>, Part I, Chapter 4, Section 1.
- [Bentz and Stutzman 1999] D.P. Bentz, P.E. Stutzman, C.J. Haecker, S. Remond, "SEM/X-ray imaging of cement-based materials," in: H.S. Pietersen, J.A. Larbiz, H.H.A. Janssen (Eds.), *Proceedings of the 7th Euroseminar on Microscopy Applied to Building Materials*, Delft University of Technology, 1999, pp. 457-466. <http://concrete.nist.gov/monograph>, Part I, Chapter 4, Section 1.
- [Bullard and Garboczi 2006] J.W. Bullard, E.J. Garboczi, "A model investigation of the influence of particle shape on portland cement hydration," *Cem. Concr. Res.*, 36 (2006) 1007-1015.
- [Bullard and Stutzman 2006] J.W. Bullard, P.E. Stutzman, "Analysis of CCRL proficiency cements 151 and 152 using the Virtual Cement and Concrete Testing Laboratory," *Cem. Concr. Res.*, 36 (2006) 1548-1555.
- [Feng and Garboczi 2004] X. Feng, E.J. Garboczi, D.P. Bentz, P.E. Stutzman, T.O. Mason, "Estimation of the degree of hydration of blended cement pastes by a scanning electron microscope point-counting procedure," *Cem. Concr. Res.*, 34 (2004) 1787-1793. <http://concrete.nist.gov/monograph>, Part I, Chapter 4, Section 2.
- [Garboczi 1998] E.J. Garboczi, "Finite Element and Finite Difference Programs for Computing the Linear Electric and Elastic Properties of Digital Images of Random Materials," NISTIR 6269, U.S. Department of Commerce, December 1998. <http://concrete.nist.gov/monograph>, Part III, Chapter 2.
- [Garboczi 2002] E.J. Garboczi, "Three-dimensional mathematical analysis of particle shape using x-ray tomography and spherical harmonics: application to aggregates used in concrete," *Cem. Concr. Res.*, 32 (2002) 1621-1638. <http://concrete.nist.gov/monograph>, Part I, Chapter 10, Section 4.

Bibliography

[Garboczi and Bentz 1999] E.J. Garboczi, D.P. Bentz, N.S. Martys, "Digital images and computer modelling," in: P-z. Wong (Ed.), *Experimental Methods for Porous Media*, Academic Press, San Diego, 1999, pp. 1-41. <http://concrete.nist.gov/monograph>, Appendix III.

[Garboczi and Bentz 2001] E.J. Garboczi, D.P. Bentz, "The effect of statistical fluctuation, finite size error, and digital resolution on the phase percolation and transport properties of the NIST cement hydration model," *Cem. Concr. Res.*, 31 (2001) 1501-1514. <http://concrete.nist.gov/monograph>, Part I, Chapter 5, Section 1.

[Garboczi and Berryman 2001] E.J. Garboczi, J.G. Berryman, "Elastic moduli of a material containing composite inclusions: effective medium theory and finite element computations," *Mech. Mater.*, 3e (2001) 455-470. <http://concrete.nist.gov/monograph>, Part III, Chapter 7, Section 7.

[Garboczi and Bullard 2004] E.J. Garboczi, J.W. Bullard, "Shape analysis of a reference cement," *Cem. Concr. Res.*, 34 (2004) 1933-1937. <http://concrete.nist.gov/monograph>, Part I, Chapter 3, Section 7.

[Neville 1995] A.M. Neville, *Properties of Concrete*. Prentice-Hall, Harlow, England, 1995.

[Taylor 1997] H.F.W. Taylor, *Cement Chemistry*. 2nd Edition. Thomas Telford, London, 1997.